

FX Harvest PRO

User manual for the FX Harvest PRO trading panel on MetaTrader 4 and MetaTrader 5.

Important: FX Harvest PRO requires valid access to the product. A standard licensed installation also uses the `FXW_HARVEST.key` file. Some optional modules are available only on MT4 or require additional files supplied with the product package.

This manual covers the main FX Harvest PRO panel. Licensed modules such as `CAPP`, `ALGO`, `MMD`, `Pyramid / Grid`, `TESTER`, `HEDGE`, `RENKO`, `FIBOX`, `FIBONACCI`, and `DIAMENTY` have separate manuals.

Description

FX Harvest PRO brings manual order entry, position sizing, trade management, and optional licensed modules into one chart-based interface. You can use the main panel without enabling an additional module.

Key features

Main functions include:

- ✓ `BUY` and `SELL` order entry
- ✓ chart lines for entry, `SL`, and `TP`
- ✓ fixed-lot, risk, amount, and margin-based position sizing
- ✓ `BE`, `TS`, `TB`, and `AT` trade-management controls
- ✓ individual and batch actions in the `Trade` panel

- ✓ a lot calculator and saved panel settings
- ✓ access to licensed modules from the horizontal panel

The panel sends or modifies trading instructions on the connected account. Check the instrument, direction, lot size, entry, **SL**, and **TP** before selecting an order button. Broker rules, available margin, spread, and market conditions can affect execution.

Installation

Use the package prepared for your platform and language:

- MT4 Expert Advisor: **MQL4\Experts\FXHarvestPro_EN.ex4**
- MT5 Expert Advisor: **MQL5\Experts\FXHarvestPro_EN.ex5**
- standard license file: **FXW_HARVEST.key** in the platform's **Files** folder

Keep the folder structure supplied in the package. Do not place the Expert Advisor or license file directly in the terminal's main folder.

1. In MetaTrader, select **File -> Open Data Folder**.
2. Close MetaTrader.
3. Copy the complete product package into the data folder, preserving its directories.
4. Confirm that the Expert Advisor is in **MQL4\Experts** or **MQL5\Experts** and that **FXW_HARVEST.key** is in **MQL4\Files** or **MQL5\Files**.
5. Copy any files required by licensed modules as described in their manuals.
6. Start MetaTrader again.
7. If FX Harvest PRO is not visible, right-click in **Navigator** and select **Refresh**.

Updating from an earlier version

Version 8.89 reads compatible settings saved by an earlier version. A legacy Take Profit mode is migrated to the corresponding **TP in pips** or **TP as R:R proportion** mode. Default values are restored only when saved settings are incompatible or cannot be read.

Terminal permissions

MT4

1. Select `Tools -> Options -> Expert Advisors`.
2. Enable `Allow automated trading`.
3. When attaching FX Harvest PRO, open the `Common` tab and enable `Allow live trading`.

MT5

1. Enable `Algo Trading` on the main toolbar.
2. When attaching FX Harvest PRO, allow algorithmic trading for the Expert Advisor.

Some package-access checks and optional functions may also require DLL imports. If FX Harvest PRO displays a permission message, enable DLL imports in both the terminal settings and the Expert Advisor properties, then use the action shown in that message.

First run

1. Open a chart for the instrument you want to use.
2. Drag `FXHarvestPro_EN` from `Navigator` onto the chart.
3. Review the input settings. For a first start, keep the defaults unless your workflow requires different risk or trade parameters.
4. Enable automated trading for the platform and the Expert Advisor.
5. Confirm that `FX Harvest PRO 8.89` and the active status appear on the chart.

The main defaults include `Fixed lot` with `0.01`, `SL` of `25.0` pips, `TP in pips` with `25.0` pips, one simultaneously opened trade, and automatic `BE`, automatic trailing by candles, and automatic trailing stop disabled. These are software defaults, not recommendations for any account or instrument.

The interface

FX Harvest PRO uses two main panels:

- a vertical trade panel;
- a horizontal settings and module panel.

Each panel has a compact and expanded layout. **Mini** switches to the compact layout, while **Dark** changes the interface theme. The vertical panel keeps its selected chart position when you change the timeframe.

Vertical trade panel

The compact layout provides the controls used most often:

- **BUY** and **SELL** open trades using the current panel values;
- **BE** moves eligible trades to the manual break-even level;
- **CA** closes all positions handled by the action;
- **C%** closes the configured percentage of a trade;
- **TS-** or **TS+** shows whether automatic Trailing Stop is off or on;
- the lot, **SL**, and **TP** fields show the values used for the next order.

The expanded layout also provides:

- **TB** to trail **SL** to a candle;
- **AT-** or **AT+** for automatic trailing by candles;
- **MTP** and **MSL** for batch movement of **TP** and **SL**;
- **C+**, **C-**, **CO**, **CP**, **CB**, and **CS** closing actions;
- the current result for the instrument in pips, account currency, and percent;
- **SCR** to save a screenshot.

Hover over a control to read its exact action before using a closing or batch command.

Horizontal settings panel

The compact layout includes:

- **SL-**, **TP-**, and **En-** to show or hide chart lines;
- **VL-** to set the candle range used by dynamic **SL** calculation;
- **LIM** and **STP** to place a pending order by clicking the chart;
- module switches: **T** (**Trade**), **R** (**RENKO**), **F** (**FIBONACCI**), **D** (**DIAMENTY**), **H** (**HEDGE**), **P** (**Pyramid / Grid**), **A** (**ALGO**), **M** (**MMD**), **C** (**CAPP**), **L** (**Lot calculator**), **B** (**FIBOX**), and **S** (**Settings**).

Only modules included in your access can be opened. A module may also have a platform or chart-type requirement.

The expanded layout adds direct controls for the lot calculation method, **SL**, **TP**, number of simultaneously opened trades, and automatic **BE** mode.

Trade panel

The **Trade** panel lists positions for the current instrument. It lets you select one or more trades and:

- close a configured percentage with **C%**;
- move selected trades to **BE**;
- close selected trades with **C**;
- reverse selected trades with **O**;
- review the result in pips and account currency.

The optional transaction comment applies to new trades and is limited to 27 characters.

Lot calculator

The **Lot calculator** calculates a position size from the selected sizing method and **SL**. Verify the returned lot against the account and broker limits before opening a trade.

Settings panel

Open **S** to manage panel settings. The panel provides **SAVE**, **LOAD**, **DEL**, **DEL ALL**, and **RESET**, as well as **Mini**, **Dark**, **Tooltips**, **Hide trades**, and **Reverse trades** controls.

The main input groups in Expert Properties are:

- **GENERAL SETTINGS** — saved panel settings, transaction ID, and points-to-pips conversion;
- **RISK** — position-sizing method and commission handling;
- **TRANSACTIONS** — **SL**, **TP**, entry, spread protection, and sound settings;
- **TRADE MANAGEMENT** — automatic and manual **BE**, partial close, and trailing settings;
- module-specific groups, including **CAPP ADVANCED**, **ALGO ADVANCED**, and **HEDGE ADVANCED**;

- ACCOUNT PROTECTION , USER INTERFACE , STRATEGY TESTER , KEYBOARD SHORTCUTS , and OTHER SETTINGS .

Change one setting at a time and verify the panel values before trading. RESET restores the software defaults.

Keyboard shortcuts

Keyboard shortcuts are disabled by default. Enable Enable keyboard shortcuts in Expert Properties if you want to use them. The default keys are:

Action	Key
Buy	B
Sell	S
Close all	C
Close open	O
Close pending	P
Close percent	5
LIMIT on click	Q
STOP on click	W
Toggle position reversal	F
Manual BE	E
Trail SL by candles	T
Screenshot	L

If `Toggle keyboard shortcuts with the tilde key ~` is enabled, use `~` to switch the shortcuts on or off.

Optional modules

- [CAPP](#)
- [ALGO](#)
- [MMD](#)
- [Pyramid / Grid](#)
- [Strategy Tester](#)
- [HEDGE](#)
- [RENKO](#)
- [FIBONACCI](#)
- [DIAMENTY](#)
- [FIBOX](#)

`CAPP` and `TESTER` are currently available only on MT4. Other modules may also have their own platform restrictions; check each module manual for its current platform and file requirements.

Frequently asked questions

Can the main FX Harvest PRO panel be used without an optional module?

Yes. The main manual-order and trade-management panel works independently of optional modules when product access is valid.

Do all optional modules work on both MT4 and MT5?

No. Platform support differs by module. In version 8.89, `CAPP` and `TESTER` are examples of MT4-only modules; check the manual for every module you use.

Where does `FXW_HARVEST.key` belong?

Place it in `MT4\Files` for MT4 or `MT5\Files` for MT5. The MT4 Strategy Tester uses its separate `tester\Files` folder.

Can the interface be reduced in size?

Yes. Use `Mini`, or enable `Auto-scale the interface` in Expert Properties.

Troubleshooting

FX Harvest PRO does not start

The panel cannot start when product access cannot be confirmed, the required file is unavailable, or terminal trading permissions are disabled. Confirm that `FXW_HARVEST.key` is in the correct `Files` folder, enable the permissions described above, restart MetaTrader, and attach `FXHarvestPro_EN` again.

If you are using the `Orbex - Wyzwanie dla Tradera` package, access level 2 is required. Level 1 means the account is covered by the offer but does not yet meet all conditions; use `Log in and increase your deposit`. Level 0 means the current trading account is not covered by the offer; use `Open an Orbex account` or `Contact your Orbex account manager`, as applicable.

The panel or some controls are not visible

The interface may be collapsed, positioned outside the visible chart area, or blocked before initialization. Expand the chart, reopen the compact panel, or set `Auto-scale the interface` to `true`, then attach the Expert Advisor again if needed.

An order is not opened from the `SL-`, `TP-`, or `En-` lines

The requested order cannot be formed when an entry, `SL`, or `TP` is on an invalid side of the market or violates the broker's minimum distance. Move the lines to a valid arrangement, verify the order values, and try again.

An optional module does not open

The module remains unavailable when it is not included in the current access, its additional files are missing, or the platform or chart type is unsupported. Open that module's manual and complete its installation and platform requirements.

License and support

License

A standard licensed installation requires an active FX Harvest PRO license and:

- `FXW_HARVEST.key`

Technical support

- Email: pomoc@fxware.pl
- Website: <https://fxware.pl>

Copyright © 2026 FXWare. All rights reserved.

Product version: `8.89`

Documentation version: `8.89-r1`

Verification date: `08.08.2026`